

# German Doppelbock

Malt Base 8 lb. DME **OR** 9.6 lb. LME

Specialty Grains: 2 lbs Munich, 1 lb. Special B, 1/8 lb. Carafoam, 1/2 lb. Carafoam

Hops: 6 HBU Perle Hop Pellets (bittering)

Suggested Yeast: White Labs European Ale Yeast , Wyeast 1338

## *Instructions:*

1. Remove crushed grains from package and put in muslin bag. Tie bag at end to allow maximum circulation. Place in minimum 1 gallon cold water, slowly bring to approx. 160 deg., hold temp for 10 min. Discard grain, add gypsum if water is soft.
2. Add malt extract , stir well to dissolve. Bring to a boil, add bittering hops, and continue boil for 75 min. Add Irish Moss and boil for 15 min. more (optional). Remove from heat.
3. Pour unfermented beer (wort) slowly into fermentation vessel containing enough cold water to total 5 gallons.
4. Let temperature drop to approx. 80 degrees. Take hydrometer reading, sprinkle or “pitch” yeast on top. Affix cover and airlock to fermenter and stabilize temp. at approx. 64 – 68 degrees.
5. Airlock should be active within 24 hours, with fermentation slowing down by the end of day 14, the clearing stage is beginning. Siphon beer into clean carboy, affix airlock and cover to keep light out and let clear for approx. 21 days @ a cooler temp (45-60 degrees).
6. When ready to bottle, boil priming sugar in approx. 1 cup water for 1 minute, add to bottom of bottling bucket, then siphon beer into the same bucket (take final hydrometer reading while siphoning into bucket). Fill bottles to 1 “ from top of bottle and cap.
7. Store beer at 67 – 70 degrees for 7 – 10 days minimum.

S.G. 1.067 — 1.072  
F.G. 1.020